

# Mobile REMM for Palm OS - README

Version 1.0

This README will be available in the MREMM group of your PC's start menu when the installation completes.

## ***Contents***

- System Requirements
- Installation
  - MS Windows Automated Setup
  - ZIP Download
- Known Issues
- Release History
- MREMM Overview
- Disclaimer

## ***System Requirements***

To install and run MREMM you need the following:

- A Palm OS colored device running Palm OS 4.0 or higher.
- 800KB of available space, either on the handheld or on an expansion card.
- Personal computer with the following installed software:
  - Software to synchronize with your handheld, e.g., Palm Desktop for MS Windows or Mac OS, or pilot-link for Linux/Unix.

NOTE for Palm Desktop users:

It is highly recommended that you use the latest version of Palm Desktop that is compatible with your version of Palm OS. Free upgrades can be downloaded from <http://www.palm.com>.

To determine the amount of memory on your Palm OS device, open the Application Launcher and select the "Info..." option from the App menu (the App menu is accessed by tapping the top-left corner of the screen, where the clock is displayed). The resulting display includes the amount of free space available on the handheld. If your device has an expansion card, change the 'Device' drop-down list to 'Card' to determine its free space.

## ***Installation***

Multiple versions of downloads are available from the REMM web site for

installing MREMM on various platforms. MREMM\_PalmOS\_Setup.exe is the setup program for MS Windows platforms, and MREMM\_PalmOS\_Setup.zip is available to support installing on Mac and Unix/Linux platforms.

Details are provided below for installing MREMM via the automated setup program provided for MS Windows, or via the Zip archive.

## **INSTALLING MREMM: MS Windows Automated Setup**

### **Quick-Start Instructions:**

1. Download and run the setup program: MREMM\_PalmOS\_Setup.exe.
2. The MREMM handheld files will be automatically loaded into the Palm Desktop install utility (Quick Install).
3. If applicable, within the Palm Desktop install utility, distribute the files as required between the handheld and expansion card.
4. Run Palm Desktop's HotSync to load the files onto your device.

### **Detailed Instructions:**

1. Download the setup program: MREMM\_PalmOS\_Setup.exe, from the MREMM web site and run it. This copies the MREMM documentation to your computer, as well as the files that must be installed onto your handheld device via a HotSync. By default, these files are located under the folder "C:\Program Files\MREMM\PalmOS", and consist of:

```
C:\Program Files
  \MREMM
    \PalmOS
      README.TXT (this file)
      \DeviceInstallerFiles
        viewer_en.prc (Palm application file)
        mremm.pdb
```

2. When the installation completes, the Palm Desktop's install utility is launched. For Palm Desktop version 4.0 or greater, this is Quick Install. It will show the MREMM Palm files that will be installed to your handheld

during the next HotSync: viewer\_en.prc, SysZLib.prc and mremm.pdb.

3. By default, the MREMM Palm files will be installed to your handheld device's memory (RAM).

If it is desired or required that the MREMM files be placed on an expansion card, change the destination within the Palm Desktop install utility. With Quick Install, you can simply drag files between the Handheld and Expansion Card area.

4. Copies of the MREMM Palm files will remain on your computer in the "\DeviceInstallerFiles" folder shown above in case you need to reinstall them on your handheld in the future. Simply double-click these files to load them into the Palm Desktop's install utility.

### **Uninstalling from MS Windows:**

Following installation via the setup program, MREMM can be uninstalled from your Windows PC via the Control Panel's Add/Remove Programs. This is dependent on the uninsXXX.exe/.dat files that are in the MREMM installation location.

### **INSTALLING MREMM: ZIP Download**

MREMM is also available for download as a Zip archive, which is universally supported on all platforms, including Mac and Linux/Unix. On a Mac, its contents can be extracted using the Stuffit Extractor product that is included in Mac OS. On Linux, use "unzip".

1. Download the zip file: MREMM\_PalmOS\_Setup.zip, and extract its contents. The directory hierarchy is the same as that shown above in the MS Windows installation details.
2. Manually load the contents of the "handheld" folder (viewer\_en.prc, mremm.pdb) into your Palm synchronization utility.
3. If applicable, within the Palm synchronization utility, distribute the files as required between the handheld and expansion card.
4. Synchronize with your handheld, e.g., run Palm Desktop's HotSync to load the files onto your device.

### **Resolving Installation Errors**

Initial release.

## ***Known Issues***

Initial release.

## ***Release History***

Application v1.0.: initial public release

## ***REMM Overview***

- REMM is a tool that helps in diagnosis and treatment of victims of mass casualty radiological/nuclear events
- Mobile REMM has only selected pages from REMM Web site - <http://remm.nlm.gov>
- See REMM Web site for much more data, images, and background material
- See REMM Web site for key "printable pages" to carry in your pocket
- See REMM downloadable version for access without the internet

MREMM currently exists as a standalone application for

- Windows Mobile PDAs (Pocket PC and Smartphone)
- Palm OS PDAs
- BlackBerry Smartphone.

## ***Feedback***

Contact us at [nlmremm@mail.nih.gov](mailto:nlmremm@mail.nih.gov) with questions/feedback.

## ***Disclaimer***

The U.S. Government does not warrant or assume any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed.

It is not the intention of NLM to provide specific medical advice to the public, but rather to provide users with information to better understand their health.

NLM does not endorse or recommend any commercial products, process, or services.